



# DE10-Standard

## OPENCV USER MANUAL



<b>Chapter 1</b>	<b><i>Introduction</i></b>	<b>1</b>
	Software Development Flow	1
	System Requirements	2
<b>Chapter 2</b>	<b><i>Execute OpenCV Demo</i></b>	<b>3</b>
	Hardware Setup	3
	Execute Hough Lines Demo	5
	Execute Camera In Demo	7
	Execute Face Detection Demo	8
<b>Chapter 3</b>	<b><i>Compile OpenCV Project</i></b>	<b>11</b>
	Compile Hough Line Project	11
	Compile Camera in Project	13
	Compile Face Detection Project	14
<b>Chapter 4</b>	<b><i>Appendix</i></b>	<b>15</b>
	Headquarter & Branches	15

# Chapter 1

## *Introduction*


OpenCV (Open Source Computer Vision) is a library of programming functions mainly used at real-time computer vision. The DE10-Standard LXDE Desktop BPS built-in the OpenCV library, so user can use the library to perform computer vision function. Also, the BPS includes the required toolchain for building OpenCV application, so developers can directly develop and execute their project on the LXDE Desktop. No cross-compile is required.

In these demonstration, all computation is performed by AMR processor. However, developers can improve the performance of critical computation by FPGA.

## Software Development Flow

**Figure 1-1** displays the software design flow block diagram. The development procedures are:

1. In LXDE Desktop, developers design their C-code software project with a generic text editor. Generally, .c and .h files are needed.
2. Create a “**Makefile**” for your software design project, so the compiler knows how to generate a final object/executable files for your project.
3. Use the build-in GNU toolchain to generate executable file
4. Execute the executable file generated in step 3.



**Figure 1-1 Design Flow**

## System Requirements

In addition to the DE10-Standard board, the following hardware are also required:

- microSD card contains LXDE Desktop Image
- VGA Monitor
- USB Keyboard
- USB Mouse
- USB Camera (Optional)
- USB Hub if three USB devices will be insert to the DE10-Standard

The LXDE Desktop Image is available at <http://de10-standard.terasic.com/cd>. Please download the image and create a LXDE to boot microSD. For details about how to create a booting micro SD card, please refer to the document **DE10-Standard\_Getting\_Started\_Guide.pdf** in the DE10-Standard System CD.

The cameras which can be supported by the LXDE desktop are listed in the link: <http://www.ideasonboard.org/uvc/#devices>. However, not all of these cameras are fully compatible with the OpenCV software. The following cameras have been tested by Terasic and they all work well on the Open CV. If users need to use camera application, choose these camera of which we have approved.

- Logitech C310
- ET USB 2760 Camera
- Genius WideCam F100

## Chapter 2

# *Execute OpenCV Demo*

This chapter describes how to execute the demo included in the LXDE Desktop BSP. There are three OpenCV demonstrations in the BSP. The three demonstrations are houghlines, camine\_in can face\_detection. For the last two demonstrations, a USB Camera is required.

## Hardware Setup

Below is the procedure to setup the demonstration

1. Make sure the MSEL[4:0] switch is set to 01010.
2. Insert the LXDE microSD card into microSD socket (J11) on DE10-Standard
3. Connect VGA Monitor to VGA output port (J9) on DE10-Standard
4. If USB Camera is used (see **Figure 2-1**):
  - ✓ Connect USB Camera to USB Port J7 or J8 on DE10-Standard
  - ✓ Connect USB Hub to another USB Port on DE10-Standard
  - ✓ Connect USB keyboard and mouse to the USB hub
5. If no USB Camera is used (see **Figure 2-2**):
  - ✓ Connect USB keyboard to USB Port J7 or J8 on DE10-Standard
  - ✓ Connect USB mouse to another USB Port on DE10-Standard
6. Power on DE10-Standard
7. LXDE Desktop will appear on the VGA monitor, as shown in **Figure 2-3**






Figure 2-1 Setup with an USB Camera




Figure 2-2 Setup without USB Camera




Figure 2-3 LXDE Desktop


## Execute Hough Lines Demo

This demonstration shows how to use OpenCV function to detect the lines in as image. In this demonstration, the detected image is given in pic1.png file. After LXDE Desktop is booted, please follow the procedure listed below to perform the hough line demonstration.

1. Open the **OpenCV** folder in the LXDE Desktop. Then, open **example** folder.
2. Double click the **hough lines** icon, as shown in **Figure 2-4**, to launch hough line demo.
3. When Execute File dialog appears, click “Execute” button as shown in **Figure 2-5**.
4. Two dialogs will appear as shown in **Figure 2-6** (If there is only one window appearing on the screen, another window may overlap below). The dialog on the left shows the original image, the processed image and the detected hough lines.



**Figure 2-4 Double click houghlines icon**



**Figure 2-5 Click the “Execute” button**






Figure 2-6 Screenshot of Hough Line demo

## Execute Camera In Demo

This demonstration shows how to use OpenCV function to real time display the image captured by an USB camera. *Note, this demonstration requires an USB camera plug-in to the DE10-Standard.* After LXDE Desktop is booted, please follow the below procedure to perform the camera in demonstration.

1. Open the **OpenCV** folder in the LXDE Desktop. Then, open **camera\_in** folder.
2. Double click the **camera\_in** icon, as shown in **Figure 2-7**, to launch camera in demo.
3. When Execute File dialog appears, click “Execute” button.
4. A dialog will appear as shown in **Figure 2-8**. The dialog will real time display the camera captured image. The frame rate is approximately 19.
5. Click **ESC** key on the USB keyboard to close the dialog.




Figure 2-7 Double click houghlines icon





Figure 2-8 Screenshot of camera in demo

## Execute Face Detection Demo

This demonstration shows how to use OpenCV function to perform face detection with an USB

camera. **Note**, this demonstration required an USB camera plug-in to the DE10-Standard. After LXDE Desktop is booted, please follow the below procedure to perform the camera in demonstration.

1. Open the **OpenCV** folder in the LXDE Desktop. Then, open **face\_detection** folder.
2. Double click the **objectDetection2** icon, as shown in **Figure 2-8**, to launch the face detection demo.
3. When Execute File dialog appears, click “Execute” button.
4. A dialog will appear as shown in **Figure 2-9**. The dialog will real time display the camera captured image and show the detected face. When face is detected, the frame rate is about 3. Multiple face detection is supported in this demonstration.
5. Click **ESC** key on the USB keyboard to close the dialog.



**Figure 2-9 Double click objectDetection2 icon**




Figure 2-10 Screenshot of face detection demo

## Chapter 3

# *Compile OpenCV Project*

This chapter describes how to compile the three demonstration projects on LXDE. The required GNU toolchain had been preinstalled on the LXDE BSP. In addition, the source code of these demonstrations are also included in the LXDE BSP. For hardware setup, please refer to Section 0 [Hardware Setup](#).

## Compile Hough Line Project

After LXDE Desktop is booted, please follow the below procedure to compile the hough line project.

1. Open the **OpenCV** folder in the LXDE Desktop. Then, open **example** folder.
2. Click the menu item **Tools→Open Current Folder in Terminal** to open terminal, as shown in [Figure 3-1](#).
3. In terminal, type “ls” to show file list, type “make clean” to cleanse temporal and target file, and type “make” to build the project as shown in [Figure 3-2](#).
4. When make is completed, binary file **houghlines** will be generated.






Figure 3-1 Open Current Folder in Terminal




Figure 3-2 Make for hough line project

## Compile Camera in Project

After LXDE Desktop is booted, please follow the below procedure to compile the camera\_in project.

1. Open the **OpenCV** folder in the LXDE Desktop. Then, open **camera\_in** folder.
2. Click the menu item **Tools→Open Current Folder in Terminal** to open terminal.
3. In terminal, type “ls” to show file list, type “make clean” to cleanse temporal and target file, and type “make” to build the project as shown in **Figure 3-3**.
4. When make is completed, binary file **camera\_in** will be generated.




Figure 3-3 Make for camera\_in project

## Compile Face Detection Project

After LXDE Desktop is booted, please follow the below procedure to compile the face detection project.

1. Open the **OpenCV** folder in the LXDE Desktop. Then, open **face\_detection** folder.
2. Click the menu item **Tools**→**Open Current Folder in Terminal** to open terminal.
3. In terminal, type “ls” to show file list, type “make clean” to cleanse temporal and target file, and type “make” to build the project as shown in **Figure 3-4**.
4. When make is completed, binary file **objectDetection2** will be generated.




Figure 3-4 Make for Face Detection project

## Chapter 4

# *Appendix*

## Headquarter & Branches

- Tel: +886-3-575-0880
- Fax: +886-3-572-6690
- Add: 9F, No.176, Sec.2, Gongdao 5th Rd, East Dist, Hsinchu City, Taiwan 300-70
- Email: sales@terasic.com / support@terasic.com